

How to Make Your Own Tassels

Editor: Liz Johnson

Friday, 23 September 2011 9:00



Tassels are the "jewelry" of home decor, adding an elegant finish to your project. And, like jewelry, they can be quite expensive to buy and the selection of colors is limited. No problem for you! Because tassels are actually very easy to make, and the embroidery floss you use to do it is inexpensive and comes in hundreds of hues and textures. We bring you this no-hassle tassel tutorial just in time for holiday sewing, which cries out for tassels on stocking cuffs and toes, ornaments, table runners and more.

Our tutorial is written for embroidery floss, but there are lots of options. We chose floss because it is easy to find, the color palette is nearly endless, and you can usually find silk, metallic and variegated options as well as the traditional cotton. That said, we have friends who love to use yarn and thread for their tassels, and they remain our friends. As they say, "All's fair in trims and tassels."

If you like the *Patchwork Table Topper with Vintage Button Trim* pictured above, you'll find the tutorial right [here](#).

Fabric and Other Supplies You Need


- Upholstery needle
- Stiff cardboard
- Embroidery floss (*you would also use thread or yarn*)
- Scissors
- Fabric glue

Getting Started


1. A tassel is made of four simple parts: the tie, the head, the wrap and the bundle.



2. Determine the finished length of your tassel and cut a piece of cardboard that is 5" wide x twice your determined length. For example, if you want your tassel to be 4" from top to bottom, cut a piece of cardboard that is 5" wide x 8" high.
3. Fold your cardboard in half. In our example, the folded piece is now 5" wide x 4" high.
4. Cut a strand of floss about 12". Most stands of cotton embroidery floss are actually made up of three twisted threads. This twisted set of threads makes up one strand.
5. Insert your 12" floss strand in between your folded cardboard. This strand will eventually become your tassel tie.



6. Wrap floss around and around the cardboard. The more you wrap, the fuller your tassel. About 80 times is a pretty good average.




Tie and Wrap and Trim

1. With one hand, hold the wrapped cardboard flat against a tabletop. With the other hand, grab both ends of your tie strand and gently pull it down and out the open end of the cardboard. Once out, you can let go with your first hand and use both hands to make a knot around the floss bundle with the tie strand.
2. With your scissors, cut along the opposite, folded edge to free your tassel from the cardboard.




3. Make two to three additional knots with the tie strand to secure, adjusting your floss bundle if necessary to make sure you're knotting as close as possible to the exact middle of the floss bundle.
4. For the wrap, cut at least a 24" strand of floss. Fold this strand in half and thread both cut ends through the end of your upholstery needle.



5. Take your floss bundle and fold it in half at the knot. Circle your wrap strand around the bundle approximately $\frac{1}{4}$ " to $\frac{1}{2}$ " from the top. This section from the top to the wrap is the head, you can adjust the size to whatever you'd like, but the rule of thumb is: the thinner the tassel, the smaller the head. Pass your needle back through the strand loop and pull tight to secure.



6. Once secured, circle your wrap strand around your floss bundle as many times as needed to achieve the look you want. Again, the look is up to you, but about eight to ten wraps is a good average.
7. When you're finished going around and around, pass your needle back through the wrapped threads and pull tight. Trim off the excess and finish with a dab of fabric glue.



8. Trim the bottom of your tassel to shorten and even edges as needed. If you want, you can also separate and fluff each strand's individual threads to fluff it out even more.
9. Use the tie strand to attach the tassel to your project.

Sewing Tips & Tricks

This project and patterns (if any) may be downloaded for personal use only. No electronic or printed reproduction permitted without the prior written consent of Sew4Home LLC.

Copyright 2009-2019 Sew4Home LLC. All Rights Reserved.